Beagle 5.1

Brian L. Browning

Department of Medicine

Division of Medical Genetics

University of Washington

August 12, 2019

Contents

C	Contentsi			
1 Introduction		1		
	Citing Beagle			
		mmand line arguments		
J				
1				
	4 Input files4			
2	5 Output files		4	

1 Introduction

Beagle is a program for phasing and imputing missing genotypes. Sporadic missing genotypes are imputed during phasing. If a reference panel of phased genotypes is used (see the **ref** argument), ungenotyped markers that are present in the reference panel can also be imputed.

Beagle 5.1 is similar to version 5.0, but includes some additional improvements that increase accuracy and reduce computation time.

Beagle 5.1 does not analyse genotype likelihood input data, and it does not perform identity-by-descent segment detection. Beagle 4.0 or 4.1 can be used to infer genotypes or genotype probabilities from genotype likelihoods, and the Refined IBD program (http://faculty.washington.edu/browning/refined-ibd.html) can be used for identity-by-descent segment detection.

2 Citing Beagle

The Beagle software program is freely available and may be downloaded from the Beagle web site:

http://faculty.washington.edu/browning/beagle/beagle.html

If you use Beagle and publish your analysis, please report the program version and cite the appropriate publication.

The Beagle 5.1 imputation algorithm is described in:

B L Browning, Y Zhou, and S R Browning (2018). A one-penny imputed genome from next generation reference panels. Am J Hum Genet 103(3):338-348. doi:10.1016/j.ajhg.2018.07.015

The most recent reference for Beagle's phasing algorithm is:

S R Browning and B L Browning (2007). Rapid and accurate haplotype phasing and missing data inference for whole genome association studies by use of localized haplotype clustering. Am J Hum Genet 81:1084-97. doi:10.1086/521987

This reference will be updated when the Beagle 5 phasing method is published.

3 Command line arguments

Beagle is run using Java version 1.8 (or later version). Enter "java –version" at the unix command prompt to check the version of java installed on your computer. The most recent Java interpreter can be downloaded from www.java.com. Attempting to run Beagle with an earlier version of Java will produce an "Unsupported Class Version" error.

To run Beagle, enter the following command at the command prompt:

java - Xmx[GB]g - jar beagle.jar [arguments]

where [GB] is an upper bound on the memory pool in gigabytes (e.g. -Xmx50g), and [arguments] is a space separated list of parameter values, each having the format parameter=value.

There are only two required command line arguments: a **gt** argument to specify the input file with genotype data and an **out** argument to specify the output file prefix. In addition, the **map** argument is highly recommended. An **ne** argument that is smaller than the default value may be necessary for best accuracy if you are analysing samples from a small or inbred population.

A reference panel with phased, non-missing genotypes can be specified with the **ref** parameter. Corresponding markers in the reference and target VCF files must have identical CHROM, POS, REF, and ALT fields, and must have the same order in both files. Before using a reference panel, you may need to run the <u>conform-gt</u> program to adjust the genomic position, allele order and chromosome strand of the markers in your data to match the reference panel.

The recommended file format for the **ref** parameter is bref3 format (.bref3) because this format gives the fastest computation time. Tools for converting between VCF and bref3 are available on the Beagle web page. Beagle will also accept reference files in Variant Call Format (.vcf) and gzip-compressed VCF format (.vcf.gz).

Reference panel markers that are not present in the input genotype data will be imputed. If you do not wish to impute ungenotyped markers, use the **impute=false** argument.

3.1 Data parameters

- ❖ gt=[file] specifies a VCF file containing genotypes for the study samples. Each VCF record must contain a GT (genotype) format field. If any heterozygote genotype is unphased (with '/' allele separator) in a marker window, Beagle 5.1 will consider all heterozygote genotypes to be unphased, regardless of the allele separator used ('|' or '/').
- ❖ ref=[file] specifies a reference panel in bref3 or VCF format. Each genotype must have two phased, non-missing alleles. If a VCF file is specified, the phased allele separator must be used '|'.
- out=[string] specifies the output filename prefix. The prefix may be an absolute or relative filename, but it cannot be a directory name.
- ❖ map=[file] specifies a PLINK format genetic map with cM units. HapMap genetic maps in PLINK format for GRCh36, GRCh37, and GRCh38 are available for download. Beagle uses linear interpolation to estimate genetic positions between map positions. If no genetic map is specified, Beagle assumes a constant recombination rate of 1 cM per Mb.
- chrom=[chrom]:[start]-[end] specifies a chromosome interval: [chrom] is the CHROM field in the input VCF file and [start] and [end] are the starting and ending positions. The entire chromosome, the beginning, or the end may be specified by chrom=[chrom], chrom=[chrom]:-[end], and chrom=[chrom]:[start]- respectively.

*** excludesamples=**[file] specifies a file containing samples (one sample identifier per line) to be excluded from the analysis.

* excludemarkers=[file] specifies a file containing markers (one marker per line) to be excluded from the analysis. Each line of the file can be either an identifier from a VCF record's ID field or a genomic coordinate in the format: CHROM:POS.

3.2 Phasing parameters

- **burnin=**[positive number] is the number of burnin iterations used to estimate an initial haplotype frequency model for inferring genotype phase (default: **burnin=6**).
- **❖ iterations=**[positive number] is the number of iterations used to estimate genotype phase (default: **iterations=12**).
- phase-states=[positive number] is the number of model states used to estimate genotype phase (default: phase-states=280).

3.3 Imputation parameters

- ❖ impute=[true/false] specifies whether markers that are present in the reference panel but absent in that target will be imputed (default: impute=true). This option has no effect if no reference panel is specified (see ref argument).
- **❖ imp-states=**[positive number] is the number of model states used to impute ungenotyped markers (default: **imp-states=1600**).
- ❖ imp-segment=[positive number] is the minimum cM length of haplotype segments that will be incorporated in the HMM state space for a target haplotype (default: impsegment=6.0).
- **❖ imp-step=**[positive number] is the length in cM of the step in centiMorgans used for detecting short IBS segments (default: **step=0.1**).
- ❖ imp-nsteps=[integer > 1] is the number of consecutive steps (see imp-step argument) that will be considered when detecting long IBS segments (default: imp-nsteps=7).
- cluster=[nonnegative number] specifies the maximum cM distance between individual markers that are combined into an aggregate marker when imputing ungenotyped markers (default: cluster=0.005).
- ❖ ap=[true/false] specifies whether AP1 and AP2 (allele probability) fields will be included in the output VCF file when imputing ungenotyped markers (default: ap=false). By default, allele probabilities are not printed because the allele dose, which is sum of the two allele probabilities, is always printed in the DS format field when imputing ungenotyped markers.
- ❖ gp=[true/false] specifies whether a GP (genotype probability) format field will be included in the output VCF file when imputing ungenotyped markers (default: gp=false).

3.4 General parameters

❖ ne=[integer] specifies the effective population size. The default value is suitable for a large outbred population (default: ne=1000000). A smaller ne parameter is necessary for accurate imputation in a smaller or inbred population.

* err=[nonnegative number] specifies the allele mismatch probability for the hidden Markov model. If no err parameter is specified, the err parameter will be set equal $\theta/(2(\theta+H))$ where $\theta=1/(0.5+\ln H)$ and H is the number of haplotypes.

- window=[positive number] specifies the cM length of each sliding window (default: window=40.0). The window parameter must be at least 1.1 times as large as the overlap parameter. The window parameter can be used to control the amount of memory required for the analysis.
- overlap=[positive number] specifies the cM length of overlap between adjacent sliding windows (default: overlap=4.0).
- ❖ seed=[integer] specifies the seed for the random number generator (default: seed=-99999).
- nthreads=[positive integer] specifies the number of threads of execution. If an nthreads parameter is not specified, the nthreads parameter will be set equal to the number of CPU cores on the host machine.

4 Input files

Beagle uses <u>Variant Call Format</u> (VCF) 4.3 for input and output genotype data, except that Beagle requires male non-pseudoautosomal X-chromosome genotypes to be coded as homozygous diploid genotypes.

Beagle assumes that an input VCF file that has a name ending in ".gz" is compressed with gzip or bgzip, and that any reference VCF file that has a name ending in ".bref3" is compressed with bref version 3.

5 Output files

There are two output files. The **log** file gives a summary of the analysis that includes the Beagle version, the command line arguments, and the running time.

The **vcf.gz** file is a bgzip-compressed VCF file that contains phased, non-missing genotypes for all non-reference samples. The output **vcf.gz** file can be uncompressed with the unix gunzip utility.

If a reference panel is specified and ungenotyped markers are imputed, the VCF INFO field will contain:

- A "DR2" subfield with the estimated squared correlation between the estimated allele dose and the true allele dose
- An "AF" subfield with the estimated alternate allele frequencies in the target samples
- The "IMP" flag if the marker is imputed